



H152-001 パイナップル風フレンチプル(L寸)

この作品はテキスト2枚です (2-1)



デザイン/松本恵衣子


- ◆使用糸 涼感クーリエ(30g玉巻)(廃番)
茶(No.8)7.4玉(220g)
- ◆使用針 ハマナカアミアミ玉付2本針5号、
片かぎ針(金属製)4/0号。
- ◆サイズ 身幅51cm、着丈56.5cm。
- ◆ゲージ 模様編み21.5目28段が約10cm角。
- ◆編み方 糸は1本どりで、指定の号数針で編みます。
身頃... 一般的な作り目で編み始め、模様編みで編み進みます。衿ぐりの伏せ目は、目を落としてから最終段をねじり目にして伏せ、肩は最終段で目を落としてから裏ねじり目で編みます。
裾・衿ぐり... 肩をかぶせはぎ(※仕上げ方ポイント参照)、脇・袖下をすくいと同じにします。前後身頃から目を拾い、縁編みで編みます。



※作り目は段数に数えない

衿ぐり

(縁編み)かぎ針4/0号




縁編み




↯ = バック中長編み
▲ = 糸を切る

バック中長編み



糸をかけ、矢印の方向に針を入れ、立ち上がりの鎖2目の長さ分だけ糸を引き出します。


引き出した糸を引っ張らないように針に糸をかけ、矢印の方向に一度に引き抜きます。




仕上げ方のポイント


肩のかぶせはぎの伏せ止めは、かぎ針4/0号でします。
そのときに目を落とした所の左右に鎖1目ずつ編みます。

- 2目1度(表目) = 左上1目交差
 - 2目1度(表目) = ねじり目(裏目)
 - 2目1度(裏目) = あとから解く目
 - 2目1度(裏目) = あとから解く目
- ~ = バック中長編み
▲ = 糸を切る




記号省略 模様編み 24段1模様






- = □表目 (Square symbol = front stitch)
- = かけ目 (Circle symbol = cast-on stitch)
- △ = 中上3目1度 (Triangle symbol = 3 stitches for 1 drop)
- ⊞ = 巻き増目 (Square with dot symbol = wrap increase)
- ⊗ = 右上2目1度(表目) (Square with top-right triangle symbol = 2 stitches for 1 drop, front)
- ⊘ = 左上2目1度(表目) (Square with top-left triangle symbol = 2 stitches for 1 drop, front)
- ⊙ = 右上2目1度(裏目) (Square with bottom-right triangle symbol = 2 stitches for 1 drop, back)
- ⊚ = 左上2目1度(裏目) (Square with bottom-left triangle symbol = 2 stitches for 1 drop, back)



記号省略 横 (Symbol omission, horizontal)



←1(拾い目) 後身頃編み終わり (←1 (pick-up stitch) back body construction finished)